



SWsoft

Parallels Power Panel

Container Administrator's Guide



(c) 1999-2008

ISBN: N/A
Parallels
13755 Sunrise Valley Drive
Suite 600
Herndon, VA 20171
USA
Tel: +1 (703) 815 5670
Fax: +1 (703) 815 5675

© 1999-2008 Parallels. All rights reserved.

Distribution of this work or derivative of this work in any form is prohibited unless prior written permission is obtained from the copyright holder.

Contents

Introduction	6
Logging In	7
Parallels Infrastructure Manager Interface Overview	8
Customizing Parallels Power Panel Interface	13
Using Parallels Power Panel Desktop	14
Customizing Parallels Power Panel Desktop	14
Container Operations	15
Starting and Stopping Container	15
Working With Container Files and Folders	16
Creating Folder	17
Creating Text File	17
Editing Text File	18
Uploading File To Container	18
Copying Files and Folders Inside Container	18
Moving Files and Folders Inside Container	18
Editing File or Folder Properties	19
Changing Container Root/Administrator Password	19
Reinstalling Container	20
Stopping Container Prior to Reinstallation	20
Selecting Reinstallation Type	21
Confirming Reinstallation	21
Repairing Container	22
Backing Up and Restoring Container	23
Creating Container Backup	24
Backup Details	24
Browsing Backup Contents	25
Updating Container Software	26
Resources Overview	27
CPU Parameters	27
Disk Parameters	28
Memory Parameters	30
Managing Container Applications	33
Managing Container Application Templates 03-02-01-03-14	33
Managing Software Packages in EZ Templates Based Container	34
Managing Container Control Panels	36
Managing Container Services and Processes	37
Managing Container Services	38
Managing Services in Linux	38
Managing Services in Windows	40
Managing Container Processes	41
Managing Container Firewall	43
Configuring Firewall in Normal Mode	44
Adding Access Rule in Normal Mode	45
Selecting Mode	45
Building Input Chain	46
Building Output Chain	48



Building Forward Chain	49
Adding Rule in Advanced Mode	49
Editing Rule in Advanced Mode	50
Installing Plesk.....	50
Working in Plesk Control Panel	50
Logging In to Plesk Control Panel.....	51
Changing Plesk Administrator Password	51
Logging In to Confirxx Control Panel	52
Using SSH to Connect to Container	53
Using Remote Desktop Connection to Access Container.....	55
 Monitoring Operations and Viewing Logs	56
Viewing History of Container Status Changes	57
Viewing Alerts Log	57
Viewing Traffic Log	58
Viewing Active Tasks.....	59
Viewing Task Details.....	59
Viewing Error Details.....	60
 Troubleshooting	61
Services Inaccessibility.....	62
Elusive Problems	62
Network Problems	63
File Problems	63
 Index	64

Table of Figures

Figure 1: Power Panel Menu.....	9
Figure 2: Power Panel Logo & Copyright Info	11
Figure 3: Power Panel Title Bar	11
Figure 4: Installing ActiveX SSH Client	53
Figure 5: Infrastructure Manager - Installing Remote Desktop ActiveX Control	55

CHAPTER 1

Introduction





The Parallels Power Panel functionality provides you as Container administrator with the ability to manage your Container(s) with the help of any standard Web browser on any platform. Parallels Power Panel allows you to manage Containers residing on Hardware Nodes running both the Windows 2003 Server and Linux operating systems. Main principles of the Parallels Power Panel operation for both operating systems are very similar. However, there are some features peculiar to only Windows 2003 Server or Linux. In case of differences between the two versions, the steps written specifically for the Windows version are marked with the  icon and the steps for the Linux version - with the  icon.

A list of supported browsers is given below:

- Internet Explorer 6.0 and above;
- Mozilla 1.7 and above;
- Firefox 1.0 and above.

Chances are that you will also be able to use other browsers, but the Virtuozzo Containers software has not been extensively tested with them.

Currently, you are able to manage your Container in the following ways:

- Start, stop, or restart the Container;
-  Mount and unmount the Container in the repair mode;
-  Reinstall the Container;
- Back up and restore the Container;
- Change the Container root/Administrator password;
- Start, stop, or restart certain services inside the Container;
- View the list of Container processes and send them signals;
- View the current resources consumption and resources overusage alerts;
- View logs and monitors for the Container;
- Customize the Parallels Power Panel interface;
-  Connect to the Container by means of RDP;
-  Connect to the Container by SSH,
- etc.

Note: Hereinafter, the root/Administrator denotation is used to identify the main user in the Linux and Windows operating systems, respectively.

In This Chapter


Logging In.....	7
Parallels Infrastructure Manager Interface Overview	8
Using Parallels Power Panel Desktop	14

Logging In

To log in to your Container, use the IP address (or hostname) and TCP port of your Container proper. Your provider should inform you of the IP address (or hostname) and TCP port to enter in the address line of your browser and of the credentials (user name and password) to use to log in to the Container.

There are two possible ways to log in to your Container:

- 1 Enter Container administrator credentials: the user name (`root` for a Linux-based Container and `Administrator` for a Container run on Windows) and the password your provider has given you.
- 2 Enter `admin` as the user name and the password of the Plesk `admin` user. This is possible only if the Plesk control panel is installed inside your Container and your provider has entitled you to do so.

 Your provider may supply you with the credentials of the Plesk `admin` user for you to use the benefits of the Plesk control panel in your Container management. If you have logged in to your Container using the Container IP address and the TCP port of Plesk (by default, it is 8443), and the Plesk control panel is not installed in your Container, you will be asked to install it after you have logged in to the Container. To do this, follow any of the links (except for the **Virtuozzo** link) on the Plesk main menu in the left part of the displayed window. You will be warned with a message saying that Plesk is not installed in your Container and offering you to install it. To complete the installation you should follow the instructions on the screen. After you have successfully installed the Plesk control panel in your Container, you can proceed with the normal course of work.

In either case, once you have connected to the Container, you are recommended to:

- 1 Change your `root/Administrator` password at once by following the **Change password** link in the left pane of the Parallels Power Panel page.
- 2 Provide a valid email address on the Parallels Power Panel configuration page to be able to log in to Parallels Power Panel if you forget your password. In case you are unable to reach your Container due to password-related problems, you can follow the **Forgot your password?** link on the login page, which requests you to enter your user name and the email address provided on the Parallels Power Panel configuration page. On filling in these fields you will receive a URL at the email address entered informing you how to change your password.

Parallels Infrastructure Manager Interface Overview

The Parallels Power Panel interface has been designed for the Container administrator to quickly perform all possible tasks through an intuitive navigation system.

All Parallels Power Panel pages have a *menu* on the left, a *toolbar* and a *status bar* on top, and the content part in the middle. If Parallels Infrastructure Manager is integrated in the Plesk control panel, the Parallels Power Panel menu will be replaced with the Plesk menu. The Parallels Power Panel menu looks like this:













Figure 1: Power Panel Menu

It provides links to Parallels Power Panel pages where you can perform various tasks. To open any of these pages, run the cursor over the link and click it. The link to the page currently open is highlighted. The description of the corresponding page is displayed at the bottom of the menu. All links are gathered into four groups: **Container Management**, **Container Services**, **Logs**, and **Other**, the names of the first three groups being links themselves. When performing a particular task, you may first click the name of the group to open the corresponding dashboard and then choose a task, or you may select the task at once on the menu under the corresponding group.

Note: If your Container resides on the Hardware Node running the Windows 2003 Server operating system, the **Firewall**, **Install Plesk** and **SSH Connection** links on the Parallels Power Panel menu are unavailable. At the same time, you can make use of the **Remote Desktop** link.

The links on the menu do the following:

Link	Description
Container Management	Opens the Container Management dashboard where you can learn more about various Container management tasks and perform any of them.
Overview	Opens the default Overview screen
Start/Stop Container	Opens the page where you can start, stop, or reboot the current Container.
Change Password	Opens the page for changing the Container root/administrator password.
File Manager	Opens the File Manager page where you can view a list of files and directories and perform all the essential file operations.
Maintenance	Opens the page where you can manage your Container backups,  recover the original template files of your Container if something has gone wrong, or  start your Container in the so-called repair mode to perform command line checks and fixes.
Resources	Opens the page where you can learn the current consumption of the hardware resources by your Container.
Container Services	Opens the Service Management dashboard, which lets you learn more about various service management tasks and perform any of them.
System Services	Opens a list of principal services inside your Container with the opportunity to start, stop, restart any of them and to control their behavior on the Container startup.
 System Processes	Opens a list of processes running inside your Container with the opportunity to send various signals to any of them.
 Firewall	Opens your firewall current settings.
 The Plesk control panel	This link is displayed only if the Plesk application template is installed in the Container being managed. It opens the Plesk control panel login window.
 Install Plesk	Open Install Plesk page that allows you to install the Plesk control panel in the Container(s).
 Confixx control panel	This link is displayed only if the Confixx application template is installed in the Container being managed. It opens the Confixx control panel login window.

 Remote Desktop	Opens a Remote Desktop session for connecting to your Container via RDP.
 SSH Connection	Opens a <code>ssh</code> terminal window for connecting to your Container via SSH.
Logs	Opens the Logs dashboard where you can learn more about various logs available for your Container and view any of them.
Status Changes	Opens a list of status changes your Container has recently undergone.
Resource Alerts	Opens a list of alerts of your Container overusing any hardware resources or coming close to the usage limits imposed on it.
Actions Log	Opens a list of actions you have recently performed in Parallels Power Panel with the current Container.
Traffic Log	Opens the page where you can view your traffic statistics for a specified period in the past.
Help	Opens this help system.
Configure	Opens the page where you can customize the Parallels Power Panel interface.
Sign out	Following this link logs you out of Parallels Power Panel.

The toolbar is to be found on every Parallels Power Panel screen to allow you to easily perform the operations most frequently required in the course of Container management with the help of the Start, Stop, Restart, Backup and New buttons.

The status bar on top is presented on the following figure:



Container foo.azshara.com

Figure 2: Power Panel Logo & Copyright Info

It consists of the following elements (from left to right):

- 1 The Virtuozzo logotype providing a link to the Parallels Power Panel main page.
- 2 The ID or the host name of the current Container.
- 3 The current state of the Container.
- 4 The percent of the available disk space used by the Container.
- 5 The Parallels copyright information.

The area in the lower right corner of any Parallels Power Panel page not covered by the menu and by the status bar provides the contents proper of the page. It has a *title bar* on top (just below the status bar), an example of which is shown below:




Figure 3: Power Panel Title Bar

It consists of the following elements (from left to right and from top to bottom):

- 1 The icon corresponding to the current Parallels Power Panel page.
- 2 The hierarchy of levels superior to the level of the current Parallels Infrastructure Manager page or the links to the pages visited prior to the page you are on. These levels or links are called the route elements. They present links for moving up to any of these levels or pages.
- 3 The name of the current Parallels Power Panel page.
- 4 The screen ID of the current Parallels Power Panel page. If you are running any trouble with Parallels Power Panel, mentioning the ID of the problem screen in your support call is likely to facilitate resolving your issue.
- 5 A link to the Active Tasks page. It opens the page with the list of those tasks related to managing your Container that you have scheduled by means of Parallels Power Panel, but that have not yet been completed.
- 6 A link to a level in the Parallels Power Panel hierarchical structure higher than the current one.
- 7 A link to refresh the current screen.
- 8 A link to open the context-sensitive help. The help window opens at the topic related to the current Parallels Power Panel page, but you will also be able to browse the entire help from this window..

The contents proper of any Parallels Power Panel page vary depending on the functions to be performed on it. The topmost-level page, which is displayed right after logging on to Parallels Power Panel, provides brief information on the current Container in the **Container Summary** table and links to the three Parallels Power Panel dashboards (see above).

Notes: 1. In case your Container is short of any resource, the corresponding warning is displayed with the link to the **Resources** page for you to check the state of resources consumption by your Container. 2. In case you have not yet provided your contact e-mail, which is necessary to enable the functionality of restoring the password, a link is provided to the page where you can do it.

The **Container Summary** table has the following fields:

Field Name	Description
ID	The ID of the current Container.
Hostname	The hostname of the current Container.
Current status	Indicates whether the Container is running, down, being repaired, or in any other state. The description of all possible Container statuses is provided in the Container Statuses section.
IP Address(es)	Specifies the IP address(es) of Container network interfaces. These address(es) are assigned by your provider.
Operating System	Indicates what operating system is running inside your Container.
Applications Installed	Enumerates additional applications installed in the Container by your provider. Shown only in case there are any.

You can also download **Parallels Power Panel User's Guide** at the bottom of the page.

CHAPTER 2

Customizing Parallels Power Panel Interface

Clicking on the **Preferences** link on the Parallels Power Panel left menu opens the Parallels Power Panel interface configuration page where you can set a number of parameters related to the Parallels Power Panel interface. The options provided on the **Configure** page are the following:

Option	Description
Interface Language	As Parallels Power Panel is localized into a number of languages, this drop-down menu lets you choose the default interface language for Parallels Power Panel. This setting affects the language of both your current Parallels Power Panel session, and all future sessions if User Default is chosen as the interface language on the Parallels Power Panel login screen.
Local Time Zone	This setting affects the date and time information found on such Parallels Power Panel pages as Status Changes , Resource Alerts , Actions Log . Choose the time zone you wish to apply when viewing different kinds of logs.
GUI Elements Style	This setting is effective for different types of GUI elements found on different screens. You may choose a visual mode for them, a textual mode, or a combination of both.
Interface Skin	Here you may choose a suitable interface skin for your Parallels Power Panel interface. The skin affects such elements as the Parallels Power Panel general layout (framed or non-framed), icons and images, and the color palette.
Status Bar Refresh	This setting affects the refreshing period of the status bar located at the top of any Parallels Power Panel page (see Parallels Power Panel Interface Overview (on page 8)). If you select the Smart Update option, the status bar will be refreshed only when you follow Parallels Power Panel links, but not more than once per 60 seconds. If this option is disabled, it means that the chosen interface skin does not use frames; therefore, it is impossible to reload only part of the page.
Contact Email	This field should be filled in with a correct email address to enable the functionality of restoring the password, should the current user forget it. This email address pertains to the current user only; other Parallels Power Panel users of the given Container may fill in this field with other addresses. The link for restoring the password is located on the Parallels Power Panel login page.

After you decide on the suitable configuration and press the **Submit** button, the settings will be remembered for the current browser only. If you change the browser or move to another computer for working with Parallels Power Panel, the default settings will be used until you perform a new customization.

Using Parallels Power Panel Desktop

The **Desktop** allows you to have the most frequently used options at hand, available and organized in such an individual way that can considerably save your time reaching them. The **Desktop** screen displays every time you log in or on clicking on the Virtuozzo logotype. The **Desktop** is a remarkably customizable environment the ultimate appearance of which can be configured on the **Customize Desktop** page (see page 14).

Customizing Parallels Power Panel Desktop

If you clicked the **Customize Desktop** icon on the Parallels Power Panel toolbar to adapt its preferences to your current needs, on the **Customize Desktop** you can use the following options.

To start with, you can set up your Desktop appearance by placing its items either in two columns or in any of them in the **Desktop Layout** subsection: select the item and click the << button to move it to the left column or the >> button to move it to the right column. To further adjust the distribution of the items, use the **Up** and **Down** buttons.

Further on, you can write, or edit, anything worth memorizing in the **Memo Contents** field - if you want this to be seen on your Desktop, select the **Show 'Memo' Section** checkbox.

To place to the Desktop an action, select this action in the **Available** table on the left of the following section and move it to the **Selected** table with the >> button. The << button takes the action selected in the **Selected** table back to the **Available** table. You can regulate the actions position on the Desktop with the **Up** and **Down** buttons.

Select the **Show 'Actions' Section** checkbox to make the actions from the **Selected** table appear on your Desktop.

If you select the **Show 'Container Summary' Section** checkbox, the Desktop will be displaying the summary information on the Container.



Finally, you can decide whether you need to have download links to the Parallels Power Panel documentation on your Desktop with the help of the **Show 'Download' Section** checkbox.

CHAPTER 3

Container Operations

The common Container operations are accessible in Parallels Power Panel from the **Container Management** dashboard. This dashboard is displayed after you click the **Container Management** link on the menu.

The following Container operations are available either by following the links under the **Container Management** group on the menu or through the links on the **Container Management** dashboard itself:

- Starting, stopping, or restarting the Container (the **Start/Stop Container** link);
- Working with Container files and directories (the **File Manager** link);
- Viewing the current resources consumption (the **Resources** link);
- Changing the Container root/administrator password (the **Change Password** link);
- Backing up and restoring the Container (the **Maintenance** link);
-  Reinstalling the original template files into the Container (the **Maintenance** link);
-  Mounting and unmounting the Container in the repair mode (the **Maintenance** link).


In This Chapter

Starting and Stopping Container	15
Working With Container Files and Folders	16
Changing Container Root/Administrator Password	19
Reinstalling Container	20
Repairing Container	22
Backing Up and Restoring Container	23
Updating Container Software	26
Resources Overview	27
Managing Container Applications	33

Starting and Stopping Container


A Container may be started up, restarted, and shut down like an ordinary computer. Depending on the Container state, only those operations are accessible that comply with its current state. For example, a running Container cannot be started for obvious reasons, and so on. The following Container states can be characterized as stable:

Status	Description
Running	The Container is running; therefore, it may only be restarted or stopped.
Down	The Container is stopped; therefore, it may only be started.


 **Repairing** The Container is being repaired. You cannot perform any action on the Container until you click the **Finish Repair** button on the **Start Container in Repair Mode** page (see page 22).




Besides these states, during Container operations a Container may be in one of the transitional states: mounting, starting, stopping, etc. When in a transitional state, you cannot perform any action on the Container until the operation is finished. The description of all possible Container statuses is provided in the **Container Statuses** section.

Click the **Start Container**, **Stop Container**, or **Restart Container** button to perform the corresponding action. On clicking one of these buttons, this action is logged.


 If you are managing a Container residing on the Hardware Node with the Linux operating system installed and wish to stop your Container, bear in mind that there is a two-minute timeout for the Container shutdown scripts to be executed. If the Container is not stopped in two minutes, the system forcibly kills all the processes in the Container. The Container will be stopped in any case, even if it is seriously damaged. To avoid waiting for two minutes if you are operating a Container that is known to be corrupt, you may use the **Power Off** link that is situated in the **Tasks** section of the Container dashboard.

Working With Container Files and Folders

For a running Container, you can navigate inside the Container directory structure, list the Container files and directories and perform all essential file operations on the **Manage Files** page. ( Right after opening this screen, you are presented with a list of drives inside the Container. Click on a drive (e.g. C:) to see its contents.) Whatever the directory you are in, the following information is given on its contents:

Column Name	Description
T	The icon in this column indicates if this is a directory or a file.
Name	The name of the directory or file.
Size	The size of the file.
Modified	The date and time of the last modification of the directory or file.
 Permissions	The first symbol in this column indicates if this is a directory (the letter d) or not (the minus sign). The following three symbols designate the permissions that the owner of the directory/file has on it, then go another three symbols for the permissions of the users belonging to the group assigned to the directory/file, and the final set of three symbols denotes the permissions of all the rest. The symbols in each of the set express consecutively the following permissions: read, write, and execute. The presence of a letter (correspondingly, r, w, or x) indicates that the permission is given, and the minus sign - that it is absent.
 User	The owner of the file/directory.
 Group	The users' group that has certain permissions on the file/folder. These permissions are presented by the 5th thru 7th symbols in the Permissions column.

Actions Hyperlinks for performing certain operations with the directory or file (see below).

 **Note:** If the Container is being repaired (see page 22), the file manager root directory (/) corresponds to the `/repair` directory of the temporary Container, in other words, it represents the root directory of the problem Container, not that of the newly-created one.

Apart from viewing a list of files and directories with their essential properties, you are able to perform the following operations:

- Create a new folder in the current directory (see page 17);
- Create a new text file in the current directory (see page 17);
- Edit existing text files (see page 18);
- Upload a file from your local computer to the current Container directory (see page 18);
- Download a file from the current Container directory to your local computer (by clicking the diskette icon in the **Actions** column);
- Copy any number of files or folders to another directory inside the Container (see page 18);
- Move any number of files or folders to another directory inside the Container (see page 18);
- Edit the properties of any folder or file (see page 19).
- Remove any number of files or folders by selecting them and following the **Remove** link.

To perform a certain operation (e.g. copying) on a number of directories or files, tick the corresponding checkboxes. The uppermost checkbox allows you to select all the directories and files at once.

Creating Folder

The page where you can indicate the name of a new folder to be created is called **Create Folder**.

Enter the folder name in the **Folder Name** field and click **Submit**. The new folder will be created in the current directory (designated above the field).

Creating Text File

The **Create File** page allows you to create simple text files directly inside the Container, without having to upload them from your local computer.

In the **Specify File** section, you should enter the name of the file to be created in the current directory (this directory is indicated under the page heading) to the **Name** field and, optionally, type the text of the file in the **Content** field. Click **Create** when you are finished to create the new file.

Editing Text File

Parallels Power Panel allows you to edit any text file inside your Container directly thru the Parallels Power Panel interface. The **Edit File** page can be accessed by clicking on the right icon in the **Actions** column for the corresponding text file on the **Manage Files** page.

This page presents the contents of the file in an editable field. Make your modifications and click **Submit** to write a new version of the file.

Uploading File To Container

The current version of Parallels Power Panel allows you to upload external files to the Container, up to ten files at a time. The **Upload File** page is displayed after clicking the **Upload File** link on the **Manage Files** page.

Click the **Browse** button, navigate to the local file you wish to upload and double-click it. The path to the file will be displayed in the corresponding **Specify File** field. Another way of indicating the file is to enter this path manually.

When you click **Upload**, the files that you have specified will be uploaded to the current directory inside the Container. For your reference, this directory is indicated above the **Specify File** group.

Copying Files and Folders Inside Container

The **Copy File(s)** page, where you can perform the copy operation, gets displayed after you have selected one or more files and/or folders by ticking the corresponding checkboxes on the **Manage Files** page and clicking **Copy**.

On the **Copy File(s)** page, click **Select** and, in the popup window, navigate to the folder where you want to copy the files and/or folders, check the radio button to the left of it, and press **Select**. The path to the target folder will be displayed in the **Destination Path** field. Click **Copy** to begin the copy process.

Moving Files and Folders Inside Container

The **Move File(s)** page, where you can perform the move operation, gets displayed after you have selected one or more files and/or folders by ticking the corresponding checkboxes on the **Manage Files** page and clicked **Move**.

On the **Move File(s)** page, click **Select** and, in the pop-up window, navigate to the folder where you want to move the files and/or folders, check the radio button to the left of it, and press **Select**. The path to the target folder will be displayed in the **Destination Path** field. Click **Move** to begin the move process.

Editing File or Folder Properties

The page where you can view and edit some properties of a certain file or folder is accessible by clicking the leftmost icon in the **Actions** column for the corresponding file or folder on the **Manage Files** page.

The information is given on the following file or folder general properties, whether editable or not:

Field	Description	Editable?
Name	The name of the file or folder.	Yes.
Path	The path to the file or folder inside the Container.	No. See Moving Files and Folders Inside Container for information on how to change the path.
Size	The size of the file. To save the time needed to open the page, a link is given for a folder to calculate its overall size.	No.
Modified	The date and time of the last modification of the file or folder.	No.



You can also change such file/folder properties as permissions and ownership.

When you click **Submit** on the **Change Properties** page, your changes will be applied to the given file or folder.

Changing Container Root/Administrator Password

The **Change root/Administrator password** page is displayed on clicking the **Change Password** link on the **Parallels Power Panel** menu. Only the root/Administrator password for the current Container can be changed. You should enter a new root/Administrator password for the current Container into the fields provided and click **Change**.

Note that **Parallels Power Panel** does not check the entered password as to its length and non-conformity to dictionary entries, so choosing a simple password rests entirely at your own risk. It is recommended to use a chaotic set of lowercase (a-z) and uppercase (A-Z) letters, digits (0-9), and punctuation marks as root/administrator password. The following punctuation marks are allowed: ! " \$ % & , () * + - . / : ; < = > ? [\] ^ _ { | }. The space character, #, and @ symbols are not allowed. The password should not be less than 5 or more than 14 characters.

Reinstalling Container

Container reinstallation means recovering the original state of a Container in case you have unintentionally modified, replaced, or deleted any file that is part of an application or OS template, and the action has brought about the Container malfunction. The Container reinstallation process restores these files as they were at the time when the Container was created or when other applications were added to the Container afterwards, if so.

Reinstallation is likely to bring about some irrevocable changes to your Container, therefore, to be on the safe side, it is recommended to back up your Container before reinstallation.

Click **Next** on the **Reinstall Container** introductory page to review the available options and to decide whether you really need to reinstall your Container and in what way.

Note: To be reinstalled, each Container has to be stopped. The description of all possible Container statuses is provided in the **Container Statuses** section. If it is not stopped, the corresponding screen will inform you of the fact. In this case follow the **Stop Container** link in the **Possible Solutions** section. Afterwards it is recommended to refresh the page by clicking the **Refresh this page** link in the **Other possible actions** section.

Stopping Container Prior to Reinstallation





The given page of the **Reinstall Container** wizard is displayed only if you have selected the **Reinstall Container** option for a running Container. Inasmuch as there is no possibility to reinstall running Containers, on this page you can stop the Container before proceeding to the reinstallation proper.

Press **Next** to stop the Container you are going to reinstall. This will take you to the page where you can view the reinstallation options and select the appropriate ones.

Selecting Reinstallation Type

The page where you should choose the mode of reinstallation is displayed after you click **Next>** on the **Reinstall Container** introductory page. You shall select one of the two reinstallation options and specify whether to preserve or drop your Container password database.

When selecting a reinstallation option, bear in mind that there is one thing both options have in common: the original files of the OS and applications templates are restored in the Container. Pay attention to the fact that any customization changes you have made to these files will be lost during the Container reinstallation. In case you have not seriously modified any system configuration files, reinstalling the original files is likely to solve many problems.

However, you have probably already filled the Container with your personal files. If you are sure these files cannot cause problems or you need them in your Container, select the first option - **Preserve the existing Container content**. In this case, your Container is created anew with all existing files moved to the /old directory or  c:\reinstall directory inside the Container. You shall be sure there is enough disk space to perform this operation, otherwise, it will fail. Be prepared to move the necessary files from the /old directory or  c:\reinstall directory to the new existing installation manually. If such files are numerous, this may prove a tedious task.

If you think you have nothing to lose at all, select the second option: **Drop the existing Container content**. Your Container will be erased and recreated from the original template(s). Naturally, all your personal files will be lost. That is why you should select this option only if you have no valuable data in your Container or if you have a backup of your personal files elsewhere.

Pay attention to the **Password Options** group. The **Preserve the password database** option retains the information on the Container users and groups. Selecting the **Drop the password database** radio button will purge this information altogether and create only the root account with the password specified in the **Set the password of root** and **Retype the password** fields under the radio button. This option may prove useful if your Container has got a corrupted password database.

When you are done, click **Next>** to proceed to the **Reinstall Container: Final confirmation** page.

Confirming Reinstallation

On the third page of the **Reinstall Container** wizard you shall confirm the reinstallation or give it up. The reinstallation option you have chosen at the previous step is displayed for you to have a last chance to revise what you are about to do. Click the **Reinstall** button to begin the reinstallation process.

Do not forget to start the Container when the operation is complete. To see the current status of the operation, click the **Active Tasks** link.

Repairing Container

Repairing a Container is another way to solve problems with the Container functioning. In Virtuozzo Containers terminology, the Container is mounted in the repair mode. This means that a new Container is temporarily created from scratch with the same network and other parameters as the broken Container, and the root directory of the broken Container is mounted as `/repair` into the newly-created Container. Thereafter, the administrator is supposed to connect to the new Container via `ssh` or Parallels Power Panel file manager (see page 16) using the network and login parameters of the broken Container, go to the `/repair` directory, and perform one of the following actions:

- 1 Find the personal data that needs to be saved and copy it to a safe location elsewhere. Do not copy your personal data directly into your new Container, as it will be destroyed once you exit the repair mode. After quitting the repair mode, the broken Container can be reinstalled and the personal data can further be loaded into it from the place where you have saved them.
- 2 Identify the source of the problem and manually correct it. This method can be recommended to advanced Container administrators, as it presupposes some technical expertise. And it is still recommended to save first your personal data in a safe location, just in case something goes wrong.

Note: When working inside the Container being repaired by means of the Parallels Power Panel file manager, the file manager root directory (`/`) corresponds to the `/repair` directory of the temporary Container, in other words, it represents the root directory of the problem Container, not that of the newly-created one.

Pressing the **Run Repair** button on the **Repair Mode** screen mounts the Container in the repair mode. It is not necessary to stop the Container beforehand; if the Container is running at the moment of pressing the **Run Repair** button, it will be first automatically stopped. The description of all possible Container statuses is provided in the **Container Statuses** section.

When the page is refreshed after pressing the **Run Repair** button, click the **Details** link at the end of the **Your Container is scheduled to start in the repair mode** message to see if the repair mode has been successfully entered. Once the Container enters the repair mode, connect to the new Container via `ssh` or Parallels Power Panel file manager and do what you deem reasonable inside the Container. After closing your `ssh` session, press the **Start Container in Repair Mode** link on the Parallels Power Panel menu once again and press the **Finish Repair** button to exit the repair mode. After the repair mode is exited, the broken Container is returned to the stopped state, and you may start it to check the repairing effect.

Backing Up and Restoring Container

Any Container is defined by its operating system files, applications installed, configuration files, and personal information. Parallels Power Panel allows you to back up all these components. A regular backing up of the existing Containers is essential for any Container reliability.

The **Maintenance** page, which allows you to perform backing up and restoring operations, opens after you click the **Maintenance** link on the main menu or selecting the **Maintenance** link on the **Container Management** dashboard accessible after clicking the **Container Management** link on the menu. If you already have backups of the given Container, it displays a table summarizing the backups.



Apart from dealing with Container backups, you may perform the operations that would guarantee the integrity and overall operability of your Container, that is reinstalling the Container (the **Reinstall Container** sub-tab) and mounting the Container in the Repair Mode (the **Repair Mode** sub-tab). To open the screen where you can check for, and, if necessary, download updates for OS and/or application packages in your Container, click the **Update Software** button.

Column Name	Description
Backed Up	The date and time when the backing up was performed.
Size	The size of the backup.
Type	Denotes if it is a full, incremental, or differential backup. An incremental backup stores not all the files and settings of the Container at the given period of time, but only the changes the Container has undergone since the last backup. A differential backup saves the data changed after the last full backup.

You can manage your backups on this page in the following ways:

- The **New Backup** button opens the **New Backup** screen where you will be able to back up the current state of your Container, be it running or not. The description of all possible Container statuses is provided in the **Container Statuses** section. This option is available only if you have not reached the maximal number of allowed backups for your Container. If you have, remove one of the backups first (see below for details). Parallels Power Panel allows you to place the backup of your Container only onto the Node where your Container is hosted.
- The **Restore Container** button restores the Container backup currently selected in the table. Only one backup should be selected for this operation. The page opened provides instructions to guide you through the process. The Container will be restored with all the values overwritten from the backup, including its IP address, password, application set, etc. The changes in the Container made after the date of this backup will be lost after the Container has been restored.

Note: If you are using an IP address of your Container to connect to it, you may have to reconnect to the Container with the IP address retrieved from the backup after the Container is restored.



- The **Remove Backups** button removes the Container backup(s) currently selected in the table. Usually this is done to provide extra space for making new Container backups. Use the checkbox at the upper left corner to select/deselect all the backups at once.
- If you have reached the limit on the number of Container backups you are allowed to create, you can make use of the **Renew Backup** button to renew a Container backup without having to delete any of your existing Container backups. By default, the oldest backup is renewed. You can also renew another Container backup by selecting the checkbox opposite the corresponding backup and clicking on the **Renew Backup** button.
- Clicking on a backup date in the table opens the **Backup Details** page where you can also restore or remove the corresponding Container backup.


Creating Container Backup

On the **New Backup** screen you are supposed to define all the parameters of the backup operation.

In the **Backup Description** section, enter any commentary you think can be practical for further backup operations.

The **Exclude** section allows you to keep certain files and directories from backing up:

-  Hidden files;
-  System files;
- Single files or directories. If you do not want to back up a whole directory, type it into the corresponding field; to add more directories to be excluded from the backup, click the plus sign.

Warning!  If you exclude one or more system or hidden files/folders from the Container backup (e.g. either the **Hidden files** or **System files** checkbox is selected), you'll be able to restore only separate files from this backup, but not the Container as a whole.

The **Include** section allows you to limit the backup process with a number of selected files or directories inside the Container. In the field provided, type the absolute path to the file or directory you wish to back up. To include additional files or directories, click the plus icon to the right of an existing path and enter a new path.

The backup will contain only those files and directories that you have indicated in the **Include** section. To back up the whole Container, leave the **Include** section empty.

Backup Details

The **Backup Details** page provides general information on the Container backup in the following table:

Column Name	Description
Creation Date	The date and time when the backing up was performed.
Backup Size	The size of the backup.

Backup Type	Denotes if it is a full, incremental, or differential backup. An incremental backup stores not all the files and settings of the Container at the given period of time, but only the changes the Container has undergone since the last backup. A differential backup saves the data changed after the last full backup.
Container	The name the Container had at the backup time. If the Container is restored from this backup, this hostname is also restored and replaces the current one.
IP Address(es)	The IP address(es) the Container had at the backup time. If the Container is restored from this backup, these addresses are also restored and replace the current one(s).
Applications Installed	All applications that had been installed in the Container by the backup time. If the Container is restored from this backup, these applications are also restored and replace the current one(s). Shown only in case there are any applications in the given Container backup.
Backup Node	The Hardware Node where the backup is stored.




To manage the backup you can use the following options on the Infrastructure Manager toolbar:

- The **Restore** button restores the Container from the current backup. The changes in the Container made after the date of this backup will be lost after the Container has been restored. Mind that you have to confirm restoring the Container on the **Restore Confirmation** page to accomplish the process.
- The **Browse** button (see page 25) allows you to browse the directory structure of the archived Container as if it had been already restored and to restore only the needed files and folders.
- The **Remove** button removes the current Container backup. Usually this is done to provide extra space for making new Container backups.

Browsing Backup Contents

Parallels Power Panel allows you to browse the directory structure of any Container backup as if this backup had already been restored and restore only the needed files and folders. The **Browse Backup** page opens after you follow the **Browse Backup** link on the **Backup Details** page (see page 24).

The contents of any directory inside a backup is presented in the table providing the following information:

Column Name	Description
T	The icon in this column indicates if this is a directory or a file.
Name	The name of the directory or file.
Size	The size of the file.
Modified	The date and time of the last modification of the directory or file.
Permissions	 The standard Linux permissions for the directory or file.
User	 The owner of the directory or file.
Group	 The owner group of the directory or file.
Actions	Allows you to download a file to your local computer provided it is not part of an OS or application template.

It is worth noting that if you are browsing an incremental backup, the information is shown not only on the files and folders from this backup, but on all the contents of the Container, should it be restored from this incremental backup. In other words, the backed up Container is always presented in its integrity and not as a collections of sporadic changes from the incremental backup.

To restore separate files and folders from the backup to the actual Container, just select them by ticking the corresponding checkboxes in the rightmost column and click the **Restore** link.

Updating Container Software

The **Update Container** page allows you to update the OS and application packages in the given Container by adding available templates updates (in the case of standard Virtuozzo templates) or updating Container packages directly (in the case of Virtuozzo EZ templates). The **Update Software** page is available on clicking the **Update Container Software** link on the Parallels Power Panel toolbar, which becomes visible if you are currently located on the **Application Templates** subtab of the **Container Software** tab.

The page will display the relevant information in one of three ways:

- 1** If no updated templates for the given Container have been installed on the Hardware Node or no updated packages are found in the repository, the page just informs you of this fact.
- 2** If the Container uses standard Virtuozzo templates and one or more updated versions of the corresponding template(s) are installed on the Node, you are able to select an updated version for adding to the Container.
- 3** If the Container uses Virtuozzo EZ templates and updated packages for the given Container can be found in the repository, you are able to select the packages that you wish to update inside the Container.


Two options for customizing the update process are available on clicking the **Configure Updating** group:

- The **Force application installation** option tells the system to perform the update even if unresolved dependencies are met during the process;
- The **Jump over several upgrades instead of adding them sequentially** option can be used if two or more sequential updates are found for this or that template.

Click **Update** to update the templates/packages you have selected for the given Container.

Resources Overview

The **Overview** sub-tab summarizes the current CPU, system and disk usage by the Container in the following table:


CPU Usage	This is a positive integer or fractional number that determines the minimal guaranteed percentage share of the CPU time your Container will receive. For stopped Containers, this parameter is not available.  Load Average for the CPU usage is the average number of active processes for the past 1, 5, and 15 minutes, respectively. Value 0.0 means that the CPU is idle, 1.0 that the CPU is fully used. Value 2.0 denotes that the CPU load exceeds the nominal value by two times.
System Usage	This is a cumulative figure presenting the average consumption of a number of critical memory-related parameters by your Container.
Disk Usage	Total amount of disk space allocated to the Container. When the space used by the Container hits the soft limit (or reaches 100% on the percent bar), the Container can be allowed additional disk space up to the hard limit during the grace period (see below for more details on the grace period). To the left of the percent bar there is a table presenting a more detailed account of the resource usage. It deciphers the percentage figure at the bar and yields the numeric data on the total amount of disk space set for the Container, the disk space consumed at the moment and the portion of the disk space that rests yet available for the Container usage.



The information on the disk usage is organized as follows:

Column Name	Description
Resource	The name of the resource: either disk space or disk inodes.
Used	Consumed disk size or the number of inodes used in the partition/logical disk.
Free	Available disk size or inodes number in the partition/logical disk.
Total	The total amount of disk size or inodes allocated for the partition/logical disk.




CPU Parameters

The CPU-related resource management is based on the following parameters:

Parameter	Description
<code>cpuunits</code>	This is a positive integer number that determines the minimal guaranteed share of the CPU time your Container will receive.
<code>cpulimit</code>	This is a positive number indicating the CPU time in percent the corresponding Container is not allowed to exceed.
 <code>burst_cpulimit</code>	The CPU power limit, in percent, the Container cannot exceed. The limitations set in this parameter are applied to the Container when it exceeds the limit specified in the <code>burst_cpu_avg_usage</code> parameter.


 <code>burst_cpu_avg_usage</code>	The CPU usage limit, in percent, set for the Container. This limit is calculated as the ratio of the current Container CPU usage to the CPU limit (i.e to the value of the <code>CPULIMIT</code> parameter) set for the Container. If the limit is not specified, the full CPU power of the Hardware Node is considered as the CPU limit. Upon exceeding the <code>burst_cpu_avg_usage</code> limit, the <code>burst_cpulimit</code> limit is applied to the Container.
 <code>cpuguarantee</code>	This is a positive integer number indicating the CPU time, in percent, the corresponding Container is guaranteed to receive. If both the <code>cpuguarantee</code> and <code>cpuunits</code> parameters are set, the <code>cpuguarantee</code> parameter is first taken into account when distributing processor(s) time among the Containers existing on the Node; the remaining CPU time, if any, is given to the Containers in accordance with the value of the <code>cpuunits</code> parameter.
<code>cpus</code>	The number of CPUs set to handle all the processes inside the given Container. By default, any Container is allowed to consume the CPU time of all processors on the Node.





The information on the available parameters is presented in the table with the following columns:

Column Name	Description
Parameter	The name of the resource parameter.
Current Usage	Indicates the consumption of the corresponding resource by the Container at the moment of calling the current Infrastructure Manager page. The units in which the consumption is measured are specified in the Units column. If the current usage is not available (<i>n/a</i>), it means that either the Container is not running, or the nature of the resource does not suggest its changing over time.
 Limit	The limit on the consumption of the given resource by the Container. The units in which the limit is measured are specified in the Units column.
 Soft Limit	The limit on the consumption of the given resource by the Container that can be exceeded only if the system is not fully loaded. The units in which the limit is measured are specified in the Units column.
 Hard Limit	The limit on the consumption of the given resource by the current Container that cannot be exceeded under any circumstances. The units in which the limit is measured are specified in the Units column.
Units	The units in which the resource values are measured.
Description	The description of the resource parameter.




Disk Parameters

The disk-related resource management is based on the following parameters:

Parameter	Description
<code>diskspace</code>	Total size of disk space consumed by the Container.  When the space used by the Container hits the soft limit, the Container can allocate additional disk space up to the hard limit during the grace period indicated by the <code>quotatime</code> parameter value.


 <code>diskinodes</code>	Total number of disk inodes (files, directories, and symbolic links) allocated by the Container. When the number of inodes used by the Container hits the soft limit, the Container can create additional inodes up to the hard limit during the grace period indicated by the <code>quotatime</code> parameter value.
 <code>quotaugidlimit</code>	Number of user/group IDs allowed for the Container internal disk quota. If set to 0, UID/GID quota will not be enabled.
 <code>quotatime</code>	The grace period for the disk quota overusage defined in seconds. The Container is allowed to temporarily exceed its quota soft limits for no more than the QUOTATIME period.
 <code>ioprio</code>	The Container priority for disk I/O operations. The allowed range of values is 0-7. The greater the priority, the more time the Container has for writing to and reading from the disk. The default Container priority is 4.

The information on the available parameters is presented in the table with the following columns:

Column Name	Description
Parameter	The name of the resource parameter.
Current Usage	Indicates the consumption of the corresponding resource by the Container at the moment of calling the current Infrastructure Manager page. The units in which the consumption is measured are specified in the Units column. If the current usage is not available (n/a), it means that either the Container is not running, or the nature of the resource does not suggest its changing over time.
 Limit	The limit on the consumption of the given resource by the Container. The units in which the limit is measured are specified in the Units column.
 Soft Limit	The limit on the consumption of the given resource by the Container that can be exceeded only if the system is not fully loaded. The units in which the limit is measured are specified in the Units column.
 Hard Limit	The limit on the consumption of the given resource by the current Container that cannot be exceeded under any circumstances. The units in which the limit is measured are specified in the Units column.
Units	The units in which the resource values are measured.
Description	The description of the resource parameter.


Memory Parameters

The memory-related resource management parameters are divided into 4 groups: memory parameters, primary system parameters, secondary system parameters, and auxiliary system parameters.

 Windows-based Containers use only the primary system parameters.





 For Linux-based Containers, this screen displays the memory-based, or the system-based, or both memory- and system-based Container resources data, depending on your settings:


- If the memory management mode is enabled for the Container, it can be allocated memory in much the same way as a certain amount of physical memory is installed on a physical computer. This is the recommended mode for managing Containers for most administrators.
- If the system management mode is enabled, the Container's performance depends on the values of quite a number of fine-grained parameters. The primary parameters are the starting point for defining the relative power of a Container. The secondary parameters are dependent on the primary ones and are calculated from them according to a set of constraints. The auxiliary parameters help improve fault isolation among applications in a Container and the way applications handle errors and consume resources.
- If both resource management modes are used, the more restrictive value is taken into account each time the system makes the decision whether to allocate this or that resource to the Container.


 *Memory parameters*

Parameter	Description
<code>slmmemorylimit</code>	An approximation of the size of the physical memory allocated to the Container. In other words, the Container performance is similar to the performance of a physical computer with as much physical memory installed as is indicated in this parameter.

Primary system parameters

Parameter	Description
<code>numproc</code>	The maximal number of processes the Container may create.
 <code>numsessions</code>	The number of simultaneous terminal sessions that can be opened to the Container.
 <code>vprvmem</code>	The size of private (or potentially private) memory allocated by the Container. The memory that is always shared among different applications is not included in this resource parameter.
 <code>numtcpsock</code>	The number of TCP sockets (PF_INET family, SOCK_STREAM type). This parameter limits the number of TCP connections and, thus, the number of clients the server application can handle in parallel.
 <code>numothersock</code>	The number of sockets other than TCP ones. Local (UNIX-domain) sockets are used for communications inside the system. UDP sockets are used, for example, for Domain Name Service (DNS) queries. UDP and other sockets may also be used in some very specialized applications (SNMP agents and others).

 **vmguarpages** The memory allocation guarantee, in pages. Container applications are guaranteed to be able to allocate additional memory so long as the amount of memory accounted as `privvmpages` (see the auxiliary parameters) does not exceed the configured barrier of the `vmguarpages` parameter. Above the barrier, additional memory allocation is not guaranteed and may fail in case of overall memory shortage.

 **avnumproc** The average number of processes and threads.

Secondary system parameters

Parameter	Description
<code>kmemsize</code>	The size of unswappable kernel memory allocated for the internal kernel structures for the processes of a particular Container.
	Note: For the Virtuozzo Containers 64-bit version for IA-64 processors, it takes 4 (four) times more the size of the kernel memory than that for the Virtuozzo Containers 32-bit version to handle one and the same process.
<code>tcpsndbuf</code>	The total size of send buffers for TCP sockets, i.e. the amount of kernel memory allocated for the data sent from an application to a TCP socket, but not acknowledged by the remote side yet.
<code>tcprecvbuf</code>	The total size of receive buffers for TCP sockets, i.e. the amount of kernel memory allocated for the data received from the remote side, but not read by the local application yet.
<code>othersockbuf</code>	The total size of UNIX-domain socket buffers, UDP, and other datagram protocol send buffers.
<code>dgramrecvbuf</code>	The total size of receive buffers of UDP and other datagram protocols.
<code>oomguarpages</code>	The out-of-memory guarantee, in pages. Any Container process will not be killed even in case of heavy memory shortage if the current memory consumption (including both physical memory and swap) does not reach the <code>oomguarpages</code> barrier.
<code>privvmpages</code>	The size of private (or potentially private) memory allocated by an application. The memory that is always shared among different applications is not included in this resource parameter.

Auxiliary system parameters




Parameter	Description
<code>lockedpages</code>	The memory not allowed to be swapped out (locked with the <code>mlock()</code> system call), in pages.
<code>shmpages</code>	The total size of shared memory (including IPC, shared anonymous mappings and <code>tmpfs</code> objects) allocated by the processes of a particular Container, in pages.
<code>numfile</code>	The number of files opened by all Container processes.
<code>numflock</code>	The number of file locks created by all Container processes.
<code>numpty</code>	The number of pseudo-terminals, such as an ssh session, screen or xterm applications, etc.
<code>numsiginfo</code>	The number of <code>siginfo</code> structures (essentially, this parameter limits the size of the signal delivery queue).

<code>dcachesize</code>	The total size of dentry and inode structures locked in the memory.
<code>numiptent</code>	The number of IP packet filtering entries.

Notes: The parameters containing "pages" in their names are measured in 4096-byte pages in the Virtuozzo Containers 32-bit version and in 16384-byte pages in the Virtuozzo Containers 64-bit version for IA-64 processors.

In the Virtuozzo Containers 64-bit versions, all the system parameter values are 64-bit and, therefore, can exceed the values in the Virtuozzo Containers 32-bit version (where the parameters values are 32-bit). For example, the limit of the `oomguarpages` parameter in the Virtuozzo Containers 64-bit version for IA-64 processors can be maximally set to 9223372036854775807 instead of 2147483647 in the Virtuozzo Containers 32-bit version. To learn more about the difference between the Virtuozzo Containers 64-bit and 32-bit versions turn to the [Virtuozzo Containers for 64-bit Processors](#) section of the [Parallels Virtuozzo Containers User's Guide](#).

The information on the available parameters is presented in the table with the following columns:

Column Name	Description
Parameter	The name of the resource parameter.
Current Usage	Indicates the consumption of the corresponding resource by the Container at the moment of calling the current Infrastructure Manager page. The units in which the consumption is measured are specified in the Units column. If the current usage is not available (<i>n/a</i>), it means that either the Container is not running, or the nature of the resource does not suggest its changing over time.
 Limit	The limit on the consumption of the given resource by the Container. The units in which the limit is measured are specified in the Units column.
 Soft Limit	The limit on the consumption of the given resource by the Container that can be exceeded only if the system is not fully loaded. The units in which the limit is measured are specified in the Units column.
 Hard Limit	The limit on the consumption of the given resource by the current Container that cannot be exceeded under any circumstances. The units in which the limit is measured are specified in the Units column.
Units	The units in which the resource values are measured.
Description	The description of the resource parameter.

Managing Container Applications


Applications can either be added to the Container by means of the corresponding Virtuozzo templates or installed in the Container as individual software packages.

Clicking **Applications** on the Parallels Power Panel menu allows you to do the following:

- view the applications added to the Container as application templates (both EZ and standard) as well as their up-to-date status.
- if some of the applications are not up to date (i.e. the updated versions of the corresponding templates or template packages are available on the Hardware Node), update them by clicking the **Update Container Software** button on the toolbar.
- add more applications available on the Hardware Node or delete unnecessary ones by clicking **Manage** and performing these actions on the screen that opens.


Managing Container Application Templates 03-02-01-03-14

Clicking **Applications** on the Parallels Power Panel menu and the **Manage** button on the screen that opens allows you to manage applications available to the Container. On this page, you can:

- View the applications already installed in the Container. These applications are listed in the **Installed/Scheduled Applications** table in the right part of the page.
- Install new applications to the Container. To add any of the applications from the **Available Applications** table to the Container, tick the corresponding checkboxes and click on the >> button. After that, the applications appear in the **Installed/Scheduled Applications** table in the right part of the page. Clicking the **Submit** button starts the installation process.
- Delete those applications from the Container that are not needed any more. To remove any application, tick the corresponding checkbox in the **Installed/Scheduled Applications** table and click on the << button. After that, the application appears in the **Available Applications** table in the left part of the page. Click the **Submit** button to start the deletion process.
-  Check unresolved dependencies among the selected applications with the help of the **Resolve** button. To eliminate unresolved dependencies, you can remove one of the problem applications from the **Installed/Scheduled Applications** table as explained above.

Note: Only standard template based Container application dependencies require resolving. If you are managing a Container based on an EZ template, the **Resolve** button is not present on the screen.

Managing Software Packages in EZ Templates Based Container

 Parallels Power Panel enables you to install, update and uninstall rpm and deb packages in Containers based on EZ OS templates. To find out what type of template the Container is based on, click the **General** tab and look at the **OS Template** in the **Container Summary** section; if it is **Standard**, this option is not available for the Container, and if it is **EZ** you will find the **Manage Software Packages** icon on the Container dashboard, on the screen that opens by the **Configuration** tab.

Note: The Container you want to manage software packages in has to be running.

Clicking this icon displays the screen where you can obtain the information on the packages currently installed in the Container in the **Installed Packages** table, presented as follows:

Column Name	Description
Name	The name of the package.
Epoch	Indicates the version of a deb package or the version of an rpm package in case the version of the rpm package is not available.
Version	The version of an rpm package.
Arch	The processor architecture; if the column shows the "noarch" value, the packet is likely to be either non-executable or contain documentation.
Summary	A short description of the package.
Status	Shows if there is a fresher version of the package: Up-to-date or Update Found .


The **Installed Packages** table displays from 10 up to 80 packages, the default number is 20 and can be changed by clicking **10**, **40**, or **80** on top of the table. To see the next portion of packages, click either the number of the page next to the one you are having at the moment, or **next** (or **last**, to view the previous page).

If the status of a package in the **Installed Packages** table suggests that an update is available, you can select this package and click the **Update** link near the table. To update all those packages that you can see on the page, select the uppermost checkbox and click **Update**. If you need to run update for all the packages installed in the Container, do not select anything - simply click the **Update All Packages** icon in the **Actions** section.

To uninstall a package, select it (or select the uppermost checkbox to uninstall all the packages listed on the page), and click **Uninstall**.

Virtuozzo can query the repository where the packages for your distribution are stored for new packages available for downloading and install them in your Container. To connect to the repository, fetch a list of the packages, see the packages description, download and install in your Container the packages you need, click the **Install Packages** icon.

Installing Software Packages in EZ Container

 Virtuozzo can connect to your Linux distribution download packages repository to form a list of packages ready to be downloaded to your host Hardware Node and installed in your Container. All these operations are available on the **Install New Packages** screen. To open this screen, click the **Configuration** tab on the Container dashboard, then the **Software Packages** icon to get the **Manage Software Packages** screen where you need to click the **Install Packages** icon.

Note: A repository can be a place where multiple files are located for distribution over a network, or a repository can be a location that is directly accessible to the user without having to travel across a network. Therefore connecting to your repository might involve either going to the web site repository (e.g. Fedora Core or Red Hat), or to the repository, created on your Hardware Node. For information on creating a local repository, refer to the **Setting Up Repository for EZ Templates** section in the **Parallels Virtuozzo Containers Installation Guide**.



On the **Install New Packages** screen you can obtain the following information on the packages:

Column Name	Description
Name	The name of the package.
Epoch	Indicates the version of a deb package or the version of an rpm package in case the version of the rpm package is not available.
Version	The version of an rpm package.
Arch	The processor architecture; if the column shows the "noarch" value, the packet is likely to be either non-executable or contain documentation.

The **Available Packages** table can display 10, 20, 40 or 80 packages, the default number is 20 and can be changed by clicking **10**, **40**, or **80** on top of the table. To see the next portion of packages, click either the number of the page next to the one you are having at the moment, or **next** (or **last**, to view the previous page).

To install a package, select its checkbox (or the uppermost checkbox, to install all the packages shown in the table) and click **Install**.

Managing Container Control Panels

There are a number of control panels that can be installed on the Hardware Node in the form of templates and added to any Container hosted on that Node. Among such control panels are Plesk,  Sitebuilder, and  Confixx.

The **Control Panels** subtab of the **Software** tab of the Container dashboard provides a single place for managing all these control panels in this particular Container. It goes without saying that the control panel template must be installed on the Node for the panel to be manageable on this screen.

The two major management operations that can be performed here are:






- adding the control panel template to the Container (the **Install** link), which ensures that this Container can be managed by the given control panel.
- logging in to the control panel to begin managing the Container with its help (the **Login** link). This is possible only if the control panel template has already been added to the Container.

Note: In the case of the Plesk control panel, the **Login** link is called **Manage** and leads to the screen where you can not only log in to Plesk but also change the Plesk admin password.

CHAPTER 4

Managing Container Services and Processes

Parallels Power Panel allows you to manage services and processes inside Containers in a number of ways by following the corresponding links on the **Container Services** dashboard. You can:

- Open a list of principal services inside your Container through the **System Services** link with the opportunity to start, stop, restart any of them and control their autostart option.
- Open a list of processes running inside the Container by clicking the **System Processes** link with the opportunity to send various signals to any of the processes.
- Log in to the Plesk control panel via the **Plesk Panel** link in case the corresponding template is installed in the Container. If the Plesk template is not installed, the **Plesk Panel** link is not displayed. Instead you can make use of the **Install Plesk** link provided in lieu of the **Plesk Panel** link to install the Plesk control panel in the Container ( this link is available for a Container running the Linux operating system).
-  Log in to the Confixx control panel by choosing the **Confixx control panel** link in case the corresponding template is installed in the Container. If the template is not installed, the **Confixx control panel** link is not displayed. The feature is available for a Linux-based Container.
-  Open an ssh terminal window with the help the **SSH Connection** link for connecting to the Container via SSH. This link is available if you are managing a Container running the Linux operating system.
-  Open a Remote Desktop terminal window through the **Remote Desktop** link for connecting to the Container via RDP (Remote Desktop Protocol). This link is available if you are managing a Container running Windows 2003 Server.
-  Open the Container Firewall page through the **Firewall** link if the Container you manage runs the Linux OS.
- Open the Sitebuilder application through the **Sitebuilder** link if the application template is installed on the Container.

In This Chapter


Managing Container Services	38
Managing Container Processes	41
Managing Container Firewall	43
Installing Plesk.....	50
Working in Plesk Control Panel.....	50
Logging In to Confixx Control Panel	52
Using SSH to Connect to Container	53
Using Remote Desktop Connection to Access Container.....	55

Managing Container Services

The process of managing services inside Container running the Windows operating system and the Linux operating system varies slightly:

- To learn how to manage services in Containers running the Linux operating system, please see the **Managing Services in Linux** subsection.
- To learn how to manage services in Containers running the Windows operating system, please see the **Managing Services in Windows** subsection.

Managing Services in Linux

 The **System Services** page is displayed after clicking on the **System Services** link on the Container Services dashboard. The page has two tabs: **Standard** and **Xinetd** (see page 39).

The **Standard** tab is used to view all the services you are running on the Container except for the `xinetd`-dependent services. To see the `xinetd`-dependent services list, click the **Xinetd** tab. By default, 20 services are shown for each tab, but you may have more services displayed by pressing the appropriate link on top of the table. You may also have the **System Services** table display only those services that have a particular name or status. On top of the table, press the **Show Search** link to display the fields where you can specify the name or the status of the service you wish to view; then click on the **Search** link.

The **Standard** page presents a table reflecting the services inside the Container and providing the following information:


Column Name	Description
Name	The system ID of the service executable file.
Status	Indicates whether the service is running or not. A green arrow means that the service is running; a red cross - that it is stopped.
Autostart	If there is a green tick in this column, this service is started automatically on the Container startup; if a red cross - it is not.

You can perform the following actions on any service in the table:

- Stop the service by selecting its checkbox and clicking on the **Stop** button. Only running services are subject to this action.
- Restart the service by selecting its checkbox and clicking **Restart**. Only running services are subject to this action.
- Start the service by selecting its checkbox and clicking on the **Start** button. Only stopped services are subject to this action.
- Enable/disable the autostart feature by clicking the name of the service in the **Name** column and opening the **Services Details** page, where you can manage the option.

Note: If you have just started the Container and opened the **Services** page, not all the services may have had enough time to start. Wait a little and refresh the page to update the state of the services.

Managing xinetd-Dependent Services

 The **System Services** page is displayed after clicking on the **System Services** link on the Container Services dashboard. The page has two tabs: **Standard** (see page 38) and **Xinetd**.

The **Xinetd** tab is used to view all the services you are running on this Container that are dependent on the `xinetd` service. To see the other services, click the **Standard** tab. By default, 20 services are shown for each tab, but you may have more services displayed by pressing the appropriate link on top of the table. You may also have the **System Services** table display only those services that have a particular name or status. On top of the table, press the **Show Search** link to display the fields where you can specify the name or the status of the service you wish to view; then click on the **Search** link.

The **Xinetd** page presents a table reflecting the `xinetd`-dependent services inside the Container and providing the following information:

Column Name	Description
Name	The system ID of the service executable file.
Status	Indicates whether the service is enabled or not. A green arrow means that the service is enabled; a red cross - that it is disabled.
Autostart	If there is a tick in this column, the <code>xinetd</code> service is started automatically on the Container startup, so is the given service; if a cross - it is not.

You can perform the following actions on any service in the table:

- Enable the service by selecting its checkbox and clicking on the **Enable** button. Only disabled services are subject to this action.
- Disable the service by selecting its checkbox and clicking on the **Disable** button. Only enabled services are subject to this action.

Viewing Service Details

The **Service Details** screen provides the principal information on the given service and lets you manage it.


The following information is provided:

- The description of the service;
- Whether the service is running or stopped;
- Whether the service is started automatically on the Container startup or not.

You may perform the following actions on any such service:


- Stop the service by clicking the **Stop Service** button. Only running services are subject to this action.
- Restart the service by clicking the **Restart Service** button. Only running services are subject to this action.
- Start the service by clicking the **Start Service** button. Only stopped services are subject to this action.
- Enable/disable the autostart feature by clicking the **Enable Autostart/ Disable Autostart** button, correspondingly.

Viewing xinetd-Dependent Service Details

 The **Service Details** screen provides the principal information on the given service and lets you manage it.

As the service is dependent on the `xinetd` service, i.e. `xinetd` is charged with launching the service when necessary, you can only either enable or disable such a service - depending on its current state - by clicking the **Enable/Disable Service** button, correspondingly. Moreover, the `xinetd` service must be running to perform any such action; otherwise, the operation will result in an error. You cannot manage the autostart feature of `xinetd`-dependent services, as its value is inherited from the `xinetd` service.

Managing Services in Windows

 The **System Services** page is displayed when clicking on the **System Services** link on the Parallels Power Panel main menu. It presents the table reflecting those services inside your Container that you can manage. The table provides the following information:

Column Name	Description
Name	The name of the service running inside your Container.
Status	Indicates whether the service is running or not.
Startup Type	Indicates whether: <ul style="list-style-type: none"> The service is started automatically on the Container startup; The startup type of the service is set to <code>SERVICE_DISABLED</code>.
Logon as	Indicates the user account (the <code>LocalService</code> account, the <code>NetworkService</code> account, etc.) that was used to start the service.

You can perform the following operations on any service in the table:

- Stop the service by selecting its checkbox and clicking on the **Stop** button. Only running services are subject to this action.
- Restart the service by selecting its checkbox and clicking **Restart**. Only running services are subject to this action.
- Start the service by selecting its checkbox and clicking on the **Start** button. Only stopped services are subject to this action.
- Open the **Services Details** page to enable/disable the autostart feature by clicking on the name of the service in the Name column.

To facilitate working with Container services, you may have the **System Services** table display only those services that have a particular name, startup type (automatic, manual, disabled), are in a certain state (running or stopped), or were started by a certain user. On top of the table, press the **Show Search** link to display the fields where you can specify the parameters your services should meet; then click on the **Search** link. To view all the services currently running inside your Container, click on the **Show All** link to the right of the parameter fields.

Changing Service Startup Type






The Service Management page opened on clicking the name of the service you have selected on the System Services page allows you to change the startup type of your Container services:

- Make a service automatically start on the Container startup by selecting the **Automatic Startup** checkbox and clicking on the **Submit** button.
- Set a service as "manual" meaning that you should start the service manually before it can be loaded by the operating system and made available for use. To this effect, select the **Manual Startup** checkbox and click on the **Submit** button.
- Disable a service by selecting the **Startup is Disabled** checkbox and clicking on the **Submit** button.

Note: Changing the default service settings might prevent key services from running correctly. It is especially important to use caution when changing the startup type of services that are configured to start automatically.

Managing Container Processes

The System Processes page is displayed when clicking on the System Processes link on the Container Services dashboard. It presents a table reflecting all the running processes inside the Container. The table provides the following information:

Column Name	Description
PID	The process ID.
%CPU	The percent of the CPU time the process is currently using.
 %MEM	The percent of the RAM size the process is currently using.
Command	The command that is used to launch the process.
 Nice	The relative priority of the process assigned to it by the user. The negative values mean that the user has manually increased the priority, the positive values - that they have decreased it.
Pri	The absolute priority of the process assigned to it by the process scheduler. On a Linux Node, the range is from 0 (the highest priority) to 39 (the lowest priority). The usual process priority is 30. On a Windows Node, the range can be from 0 (the highest priority) to 31 (the lowest priority). The usual process priority is 8.
RSS	(Resident Segment Size) The size of physical memory the process really uses (in Kilobytes).
 Stat	The state of the process. The possible states are: R - runnable, on the run queue; S - sleeping; T - traced or stopped; D - uninterruptable sleep; Z - defunct, "zombie". If two letters are shown, the second letter means the following: W - has no resident pages; < - high-priority process; N - low-priority task; L - has pages locked in memory; s - the process is a session leader; "+" means the process is in the foreground process group of its control terminal.
Time	The total amount of the CPU time the process has used so far.
User	The user the process belongs to.

To have the information in the table refreshed automatically with the current values, click the **Enable Autorefresh** button. It is worthy to note that only the table on the current page is refreshed, which takes much less resources in comparison with refreshing the whole Parallels Infrastructure Manager page.




On a Windows Node, you may select any number of processes by ticking the checkboxes against the corresponding processes (tick the uppermost checkbox to select all the processes at once) and end them by clicking the **End Process** button.



On a Linux Node, you may select any number of processes by ticking the checkboxes against the corresponding processes (tick the uppermost checkbox to select all the processes at once) and send them a standard signal. Choose the needed signal on the drop-down menu and click the **Send Signal** button. The following signals can be sent:

- **SIGHUP** - is a hang-up signal. It is often used to ask a daemon process to re-read its configuration.
- **SIGTERM** - sends the termination signal to the process. This is the best way to give the process a chance for an orderly shutdown and proper data saving. As the process might be able to catch this signal and stay alive, you may have to make use of the `sigkill` or `sigint` signals.
- **SIGCONT** - continues the process causing it to resume.
- **SIGSTOP** - stops (suspends) the process. The process will still be on the task list.
- **SIGINT** - causes the process to immediately interrupt. The signal is very close to `sigkill`, the difference being that, unlike `sigkill`, it can be caught by the process and ignored if the process gets out of hand. In this case you should send `sigkill` to shut down the process.
- **SIGKILL** - unconditionally kills the process. Mind that sending `sigkill` to any process removes any chance for it to do a tidy cleanup and shutdown, which might have unfortunate consequences.

Managing Container Firewall

 A firewall is part of your OS and its security. Its main function is to block or permit traffic between two systems or two parts of a network. A firewall is either a program (or a set of programs) or a computer it runs on. The Virtuozzo Containers software has a built-in firewall that can be managed through both Parallels Power Panel and Parallels Infrastructure Manager. Along with - and apart from - the Parallels Power Panel and Parallels Infrastructure Manager web interface a command line is an effective tool to manage a firewall. Here are the basic principles that make a firewall work.

A firewall applies a control *policy* over the firewalled system. There are three policies:

- *accept* the packet: if the packet is accepted, it gains access to the system;
- *drop* the packet: if the policy is to drop the packet, the packet is denied access to the system;
- *reject* the packet: the system does not let the packet in, notifying the sender of the fact;

The policies, along with ports and protocols, are chains' attributes. A *chain* is a list (or a chain) of rules grouped by the criterion of what type of packets they process. There are three packets types:

- *input*;
- *output*;
- *forward*.

Therefore we can create three chains - the Input chain, the Output chain and the Forward chain. The Input chain examines the incoming packets. If there is a rule to process a packet, the latter is either let in (accept policy) or not (drop/reject policy). Otherwise, the packet is examined by the next rule. If, finally, there is not any rule to match, the default system policy is applied. The first rule applied to a packet is the first one on the list that forms a chain.


If a packet is created inside the system, it is sent to the Output chain.

Packets that pass through the system, traverse the Forward chain.

When configuring a firewall, you can change a rule's position on the list, delete a rule from the list, create, edit and add rules to the list.

To configure the firewall, click on the **Firewall** link on the Container Services dashboard.

Configuring Firewall in Normal Mode

 In the normal mode the rules you delete or add are called *access rules*. The Container access rules are pre-set groups of standard firewall rules. Each access rule refers to a most widely used service and corresponds to a number of standard firewall rules that ensure the availability of this service. In the normal mode each access rule is dealt with as a single entity. This implies that enabling or disabling an access rule results in enabling or disabling all the standard firewall rules it corresponds to. By default, 6 preset access rules are active:

- 1 Access to outer world;
- 2 DNS server;
- 3 Mail server;
- 4 POP3 server;
- 5 SSH server;
- 6 WEB server.


The remaining access rules that are not enabled by default can be added on the page, which you can access by clicking **Add access rule**.

To delete a rule, select one of the check boxes on the right of the screen, click **Delete** over the check boxes, and then **OK** to confirm. To delete all the rules, select the uppermost check box, click **Delete** over the check boxes, and then **OK** to confirm. Note that no access rules can be permanently deleted from the system. A *deleted* rule is, in fact, temporarily disabled and can be enabled back as described on the **Adding Access Rule in Normal Mode** subsection (on page 45).

To change the mode, click **Firewall Setup**.

Note: If this page informs you that you cannot manage firewall on this Container, refer to the **Dealing With Misconfigured Firewall** subsection.


Dealing With Misconfigured Firewall

 If your firewall has not been configured yet, you will most probably have the page informing you of the fact. The page can also appear if you did misconfigure your firewall. The common way to misconfigure a firewall is to add or edit your own specific rules in the advanced mode and then switch to the normal mode without deleting these rules first.


At this point you will have to decide upon one of two basic strategies: to select the normal mode or to select the advanced mode:

- select the normal mode to deny all services except those critical to connecting to the Internet. To select the normal mode, click **Switch the firewall back to the normal mode**.
- select the advanced mode to create a rule to permit, deny, or monitor the access to or from the system for each service you need. If you are going to separately edit each rule, click **Select the advanced firewall mode**.

Adding Access Rule in Normal Mode

 To open this page, follow the **Add Rule** link on the **Firewall** page. Here you have the rules that have not been included into the list of active rules you can see on the **Firewall** page. To *add* a rule here means actually to *enable* it. To add a rule, select a check box on the opposite and click **Submit** - or **Cancel** if you want to restore the firewall settings prior to the last action.

Selecting Mode

 If you have only just started using the firewall by clicking the **Firewall** link on the Container Services dashboard, the **Firewall Setup** page is the first one you have displayed.


On the **Firewall Setup** page, you can choose one of the following modes your firewall operates in:

- The normal mode. If the security strategy you are planning out does not require a complicated system of specific rules and all you are going to do is as simple as providing your system with access to the Internet and the maximum safety, then the best option is the normal mode. Hence, select the normal mode to configure your firewall using the 15 built-in access rules (see page 44) or to fix the firewall rules settings corrupted either in the advanced mode or in the normal mode.
- The advanced firewall mode with default policy Accept, or the advanced firewall mode with default policy Drop. The advanced mode takes more time and experience to configure, but then there is more flexibility and potential in it to make use of.

Besides, the **Firewall Setup** page can be reached with the **Firewall Setup** link from both advanced and normal mode pages. If so, the choice is quite the same. The only difference is that in this case the normal mode can also be used as an option to reset to if you want to roll back the changes in the firewall rule(s) settings you have made.

After selecting a mode, click **Submit**. Click **Cancel** to return to the previous screen.

Building Input Chain

 To build and edit the *Input Chain*, select the **Input** tab. When you click either **Advanced firewall mode with default policy Accept** or **Advanced firewall mode with default policy Drop**, on the page described in the **Selecting mode** subsection (see page 45), the first chain of rules is the *Input Chain*. The *Input Chain* is a set of rules for the incoming traffic.

Here you can edit, add, delete, enable, disable, filter or change its position in the list of any or all of 9 default rules the input chain consists of. In case you need to come back to the original advanced mode settings, the default rules are:



- 1 Web server input;
- 2 SSH server input;
- 3 Mail server input;
- 4 POP3 server input;
- 5 DNS server tcp input;
- 6 DNS server udp input;
- 7 All tcp input for hi port allowed;
- 8 All udp input for hi port allowed;
- 9 Default system policy.

If, for some reason, you need to have this rule set back, click **Firewall setup** and select the **Normal firewall mode** radio button.

The table below describes the attributes of the rules in the chain:


Name	Description
Name	The name of a specific web service this rule applies to
Policy	One of three policies: Accept, Drop or Reject
Protocol	One of two protocols used for package transmission - Transmission Control Protocol (TCP), defined by IETF RFC793 or User Datagram Protocol (UDP), defined by IETF RFC768
Source Address	The internal address of the packets (e.g.: IPv4 or IPv6 address, the name of a network interface, etc.)
Source Port	The internal port of the packets
Destination Address	The address where the packets are sent to
Destination Port	The port where the packets are sent to
Status	The current status of the rule (Enabled/Disabled)
Move	Moving the rule a level up or a level down from its current position

The default system policy access rule cannot be changed as this rule decides the packet's destiny - to accept or to drop - when the packet has not any other rule to be processed by.

To edit a rule, click its name in the **Name** column. To add - or replace - a specific rule, click **Add Rule** in the **Actions** group. To disable, enable or delete a rule select its check box and then click **Disable**, **Enable** or **Delete**. To move a rule a level up its position, click . To move a rule a level down its position, click . To filter rules by the policy, the protocol, or the current status, click the **Show Search** link. You can have Parallels Infrastructure Manager display only those parameters you need at the moment. To show or hide certain columns, click the **Select Columns** link and select the parameters you want to be displayed or clear those you do not.

You can also switch to the normal mode by clicking **Firewall setup** and selecting normal mode there.

Building Output Chain



 To build and edit the Output Chain, select the **Output** tab. The output chain regulates the outbound access. The default rules list is the same as in the **Input Chain** (see page 46), the only difference being the *output*, instead of the *input* characteristic of the rules. The list of rules on this page is this:

- 1 Web server output;
- 2 SSH server output;
- 3 Mail server output;
- 4 POP3 server output;
- 5 DNS server tcp output;
- 6 DNS server udp output;
- 7 All tcp output allowed;
- 8 All udp output allowed;
- 9 Default system policy.

The default system policy access rule cannot be changed as this rule decides the packet's destiny - to accept or to drop - when the packet has not any other rule to be processed by.


If, for some reason, you need to have this rule set back, click **Firewall setup** and select the **Normal firewall mode** radio button.



The attributes of the rules in the chain are described on the **Building Input Chain** subsection (see page 46).

Here you can edit, add, delete, enable, disable, filter or move in the list any or all of the 9 default rules the output chain consists of. To edit a rule, click its name in the name column. To add a specific rule, click **Add Rule** in the **Actions** group. To disable, enable or delete a rule select its check box and then click **Disabled**, **Enabled** or **Delete**. To move a rule a level up its position, click . To move a rule a level down its position, click . To filter rules by the policy, the protocol, or the current status, click the **Show Search** link. You can have Parallels Infrastructure Manager display only those parameters you need at the moment. To show or hide certain columns, click the **Select Columns** link and select the parameters you want to be displayed or clear those you do not.

You can also switch to the normal mode by clicking **Firewall setup** and selecting normal mode there.

Building Forward Chain


 To build and edit the Forward chain, select the **Forward** tab. Unlike the Input and Output chains, the only default rule the forward chain has is **Default system policy**. Conceivably, this one is not to be edited or deleted. Instead, you are free to decide upon any number and kinds of specific rules to create and add to the Forward chain by clicking on the **Add Rule** link in the **Actions** group.

After the number of rules in your Forward chain becomes bigger, you may need to sort them out. To do that, click the **Show Search** link and pick the three possible values from the three drop-down menus: the policy, the port, and the current status of the rule(s). You can have Parallels Infrastructure Manager display only those parameters you need at the moment. To show or hide certain columns, click the **Select Columns** link and select the parameters you want to be displayed or clear those you do not. Click  to take a rule a level up its current position in the chain, or  to relocate it a level down. If two or more rules can be applied to the given packet, the uppermost rule takes priority.

To switch to the normal mode of managing the firewall, click **Firewall Setup** link in the **Actions** group.


The default forward chain policy is the policy selected on the **Firewall Setup** (on page 45) menu.

Adding Rule in Advanced Mode

 To get to this page, click the **Add rule** icon on the **Input Chain** (see page 46), **Output Chain** (see page 48), or **Forward Chain** (see page 49) pages. On this page you can elaborate your own specific rule. Below are the basics of the advanced mode rules adding:


- the **Name** field is marked because this field is an obligatory one;
- **Source Address and Netmask**, **Source Port or Port Range**, **Destination Address and Netmask** and **Destination Port or Port Range** fields are left to your own discretion, but in case of an error there is a pink stripe over the field that has to be corrected;
- the standard format for **Source/Destination Address and Netmask** field is 1.2.3.4/255.255.23.4;
- the standard **Port range** format is 80-123;
- to enable a rule, select the **Enable** check box;
- if you are creating this rule for future purposes, clear this box;
- to include the rule into one of three chains, select **Input**, **Output**, or **Forward** on the drop-down menu;
- on the **The rule's position in the chain** drop-down menu you are to decide what priority this rule will have in its chain. There are two options for you to choose between: the bottom and the top of the chain;
- for the changes you have made to become operational, click **Submit**, to undo the changes and return to the previous page, click **Cancel**.

Editing Rule in Advanced Mode

 The main difference here from the operations described in the **Adding Rule in Advanced Mode** subsection (on page 49) is that the rules you edit are not those you create as you deem it expedient. If you edit a rule (with the exception of renaming it), the rule changes and works differently from the way it did. Before submitting the new settings make sure they meet your security strategy. Otherwise, click **Cancel**.

The other detail to be aware of is the possible consequences of changing the initial (default) firewall settings. If you feel your expertise in the security area permits some future development, do not change them at all. Applying the changes you are not completely certain of may decrease your system's security.

Installing Plesk

 The **Install Plesk** page allows you to install the Plesk control panel in the Container. This page can be accessed by clicking the **Install Plesk** link on the **Control Panels** tab of the Container Management dashboard, which is displayed if the Plesk template is not installed in the Container. To install Plesk in a Container, you should press the **Install** button on the **Install Plesk** page. Just follow the instructions on the screen to complete the installation. After you have successfully installed the Plesk control panel in the Container, the **Plesk Panel** link becomes visible on the **Parallels Power Panel** menu. Follow this link to start working in Plesk.

Note: For the Plesk installation to be possible, the Container should be running. Moreover, you can install Plesk only if authorized to do so by your provider. If you have any problems initializing the Plesk control panel auto install, seek your provider's help. Mind though that the Plesk auto install denial may be due to the shortage in your Container resources. To check if this is the case, you can go to the **Viewing Resource Alerts Log** page where you'll be informed in the **Description** column which parameter has caused the auto install failure. You might have to consider the possibility of killing some unnecessary memory-demanding process from the Container or ask the Node administrator to allocate more resources as needed to run Plesk on your Container.


Working in Plesk Control Panel

In case the Plesk control panel is installed inside the Container, the **Plesk control panel** link becomes visible on the **Parallels Power Panel** menu. You can click on this icon to go to the Plesk control panel page.

On this page you can use the **Login to Plesk** link to start a Plesk control panel session. A new browser window with the Plesk control panel is launched and you are able to get straight down to work there.

To change the Plesk admin password, click the **Change Password** link on the **Plesk Control Panel** page. Setting a new password from time to time is recommended to assure the maximum security of a Container.

Logging In to Plesk Control Panel

 Using the **Login to Plesk** link on the Plesk control panel page you can open a pop-up window to start managing the Container via Plesk.


In this window, you should open the **Login to Plesk** link to start a Plesk control panel session. A new browser window with the Plesk control panel is launched and you are able to get straight down to work there.

The logging in to Plesk is performed automatically, you do not need to enter the name and password of the admin user since you have already been identified by your Parallels Power Panel user credentials.

You might wish to change the Parallels Power Panel user Plesk admin password used to log in to Parallels Power Panel via Plesk. The **Change Plesk Admin Password** page allows you to change the current password of the admin user, which should be done from time to time to maintain the maximum security of the Container.

Note: If your Plesk version is lower than 7.0.2, the option of changing the admin password is not provided for Parallels Power Panel.

Changing Plesk Administrator Password


 Although logging in to Plesk from Parallels Power Panel is performed automatically and does not require specifying the credentials of the admin user, the Plesk admin user name and password may be of use for a Parallels Power Panel user willing to directly log in to the Container via Plesk (see page 7). To maintain the maximum security of the Container, it is recommended to change occasionally the current password of the admin user. The **Change Plesk Admin Password** page opened through the **Change Password** link on the **Plesk Control Panel** page allows you to edit the administrator password.

To set a new password, you need to type it into the **New admin password** field and then retype it in the **Retype new admin password** field below to ensure you have provided a correct password. The password should be no less than 5 characters and difficult enough to guess to guarantee the privacy of the Container.

After you have entered a new admin password, press **Change** to submit the changes made.

Note: If your Plesk version is lower than 7.0.2, the option of changing the admin password is not provided for Parallels Power Panel.

Logging In to Confixx Control Panel


 In case the Confixx control panel is installed inside the Container, the Confixx control panel icon becomes visible on the Parallels Power Panel menu. You can click on this icon to go to the Confixx control panel login window.

In this window, you should enter your credentials (login and password) into the corresponding fields and press the **Login to Confixx** button. You may learn the credentials from your provider. In case the credentials entered are correct, a new browser window with Confixx control panel is launched and you are able to get straight down to work there.

If you select the **Save Login data** checkbox, you won't have to type your login and password again when you later visit this page - the credentials will be filled in automatically. In this case, the credentials information is stored not on the server, but on the client side (i.e. on the computer where your browser window is launched).

Note: The Confixx control panel with version below 3.0 is not supported.

Using SSH to Connect to Container

 If you are managing a Hardware Node with the Linux operating system installed, you can use Secure Shell (`ssh`) to remotely connect to the Container you are operating and work inside its directory tree using standard Linux command line tools. To connect to the Container by `ssh`, you should make sure that:

- 1 You are launching Parallels Power Panel in Internet Explorer 5.0 or above. SSH connection to the Container is supported by other browsers only if you have a Java Virtual Machine on your computer.
- 2 The Container is running. If it is not, start it on the **Start/Stop Container** page.

Note: If the Container you are managing resides on a Hardware Node running Windows 2003 Server, please turn to the **Using Remote Desktop Connection to Access Container** section (on page 55) to learn to manage a Container by means of the Remote Desktop Protocol.

The SSH Connection window is opened upon clicking on the **Terminal Login** icon on the Parallels Power Panel menu. You are presented with the **Login** and **Password** fields where you should enter the relevant information (`root` or any other user name you might have created for this Container and this user's password) to be passed to the `ssh` server inside the Container.

After you have filled in these two fields, click the **Login** button. If you are doing this for the first time, your browser may display a window like this asking you to install additional components:





Figure 4: Installing ActiveX SSH Client

Note: When SSH-connecting to your Container using a browser other than Internet Explorer, this window does not appear. The SSH connection through browsers on the Mozilla engine is provided by the Java technology.

Click **Yes** in this window and wait for the `ssh` terminal window to appear, whereupon you get connected to the Container and may start sending commands to it via `ssh`.

Using Remote Desktop Connection to Access Container

 You can use Remote Desktop Connection - a standard Windows application - to connect to the Container by means of the Remote Desktop Protocol (RDP). The feature is available only for Internet Explorer 5.0 or above. It is not supported by other browsers. To connect to the Container via RDP, you should make sure that the Container is running. If it is not, start it.

Note: If you are managing a Linux-based Container, please turn to the [Using SSH to Connect to Container](#) section (on page 53) to learn to manage the Container by means of Secure Shell.

The Remote Desktop window is opened upon clicking on the Open Remote Desktop Connection icon on the Parallels Power Panel menu. You are presented with the Login button that you should click to open a Remote Desktop session. If you are doing this for the first time, your browser may display a window like this asking you to install additional components:



Figure 5: Infrastructure Manager - Installing Remote Desktop ActiveX Control

Click Yes in this window and wait for the Remote Desktop terminal window to appear, whereupon you will be presented with the Login and Password fields. After entering the necessary information (Administrator or any other user name you might have created for this Container and this user's password) in the fields provided, click Enter to get connected to the Container and start sending commands to it via Remote Desktop.

CHAPTER 5

Monitoring Operations and Viewing Logs

Parallels Power Panel is able to display four kinds of logs maintained for your Container:

- **History of Container Status Changes.** This log reflects such changes as starting, stopping, rebooting the Container, or mounting it in the repair mode. These changes may have been invoked either through Parallels Power Panel or by other means.
- **Quality of Service Alerts.** This log reflects those states of your Container when it hits limits on some hardware resource. To know more about resources, read the **Monitoring Container Resources** section (on page 27).
- **Actions.** This log reflects only those actions related to Container management that were performed by means of Parallels Power Panel.
- **Traffic Log.** This log allows you to display your network traffic statistics for a specified period of time.

You may view all these logs by following the corresponding links from the **Logs** dashboard accessible by clicking the **Event Manager** link on the Parallels Power Panel main menu.

You can also monitor the Container operations that are either currently under way or have already been completed by viewing:

- **Active Tasks.** This monitor provides the information on any Container operation currently under way.
- **Task Details.** This monitor lets you see details not only on the real-time Container operations but on the ones already completed as well. It provides information on the Virtuozzo utilities messages during this or that operation performance.

Parallels Power Panel also provides specific information in case of an operation failure for you to learn the error cause(s).

In This Chapter

Viewing History of Container Status Changes	57
Viewing Alerts Log.....	57
Viewing Traffic Log	58
Viewing Active Tasks	59
Viewing Task Details.....	59
Viewing Error Details	60

Viewing History of Container Status Changes

The **Status Changes** page (accessible by clicking the **Status Changes** link on the Logs dashboard) keeps track of all the changes in the status of the Container. These changes may happen due to the Container routine management via Parallels Power Panel, or due to the operation of some programs. The three-column table presents the time when the Container status changed, the old status of the Container, and the status obtained. By default, 20 records are shown, but you may have more records displayed by pressing the appropriate link on top of the table. The description of all possible Container statuses is provided in the **Container Statuses** section.

You may have the **Status Changes** table display only those log records that have a particular date and time. On top of the table, press the **Show Search** link to display the fields where you can specify the boundaries of the time interval for which you wish to view the log; then click on the **Search** link.

Viewing Alerts Log

Every time a Container consumes more of a resource than is specified by the limit on that resource, or is coming close to that limit, an alert is generated and logged. Turn to the **Resources Overview** section (on page 27) to know more about the limits for corresponding resources. You shall pay attention to the problem resource and correct the situation.

The alerts log is shown on the **Resource Alerts** page available on clicking the **Resource Alerts** link on the Logs dashboard.

You may have the **Resource Alerts** table display only those alerts that have a particular date or are generated for a definite resource parameter. On top of the table, press the **Show Search** link to display the fields where you can specify the boundaries of the time interval or the resource parameter for which you wish to view the log; then click on the **Search** link.

The **Resource Alerts** table provides you with the following data:

Time	The date and time when the alert was generated.
Type	The alert sign displays the type of alert for the Container. See the Resources Overview section for more details on the existing alert indicators.
Parameter	The type of the Container resource that required the consumption value alert.

Note: There are certain correspondencies between the alert zone indicators and the alert signs in the **Type** column. A green circle with a white tick stands for the green zone, an orange circle with a white exclamation mark points to the yellow zone, and a red circle with a white exclamation mark refers to the red zone. Depending on the parameter under alert, you can learn more about alert zones on the relevant resource type in the **CPU Parameters**, **Memory Parameters**, or **Disk Parameters** subsections of the **Resources Overview** section (on page 27).

Viewing Traffic Log

The **Traffic Statistics** page enables you to view the information on all incoming and outgoing traffic for your Container over a specified time period in the past. This page can be accessed by clicking the **Traffic Log** link on the Parallels Power Panel main menu.

To display traffic statistics, you should perform the following operations:


- 1 In the **Show traffic for** field, specify the time span for which you wish to see your traffic by selecting the corresponding duration unit on the drop-down menu. Depending on the selected unit, the field to the right of the drop-down menu changes and offers you a list of appropriate values to choose from. The duration units are listed below:
 - **Day:** Click on the calendar and specify the exact date (i.e. day, month, and year) for which you wish to view your network traffic statistics.
 - **Month:** Specify the month and year to display your traffic statistics for.
 - **Year:** Specify the year to display your traffic statistics for.
 - **Period:** Specify the period for which you wish to view your traffic statistics by selecting the start and end dates on the calendar.
- 2 In the **Traffic unit** field, specify the unit of measurement your traffic statistics will be displayed in.
- 3 Click on the **Update** button to display your traffic statistics for the specified period.

The results will be presented in the following table:

Column Name	Description
<Period>	Denotes the specified period. The name of this column depends on the duration unit selected in the Period field.
Incoming	The input traffic statistics (in the selected unit of measurement) during the specified period. This is the traffic that comes to the Container from the Internet (e.g. requests from Internet surfers' web browsers to display a Container website page).
Outgoing	The amount of output traffic (in the selected unit of measurement) during the specified period. This is the traffic that goes out of the Container to the Internet (e.g. the Container website pages sent to be displayed in the Internet surfers' web browsers).

The **Total** row at the bottom of the table summarizes all the incoming and outgoing network traffic for the specified time span.

Viewing Active Tasks

Almost all Parallels Power Panel pages, except for those containing an error report, allow you to check for any Container operations currently under way. The **Active Tasks** window can be accessed by pressing the  icon at the right end of the title bar of a Parallels Power Panel page. Note that the icons vary according to the interface skin selected. If you are planning to perform any operation on your Container, it is a good idea to check the **Active Tasks** window and wait for the tasks to complete, if there are any. The window is refreshed every few seconds.

By default, 20 operations are listed, but you may have more operations displayed by pressing the appropriate link on top of the table. You may also have the **Active Tasks** table display only those operations that have a particular status. On top of the table, press the **Show Search** link to display the field where you can specify the status of the operation you wish to view the information on; then click on the **Search** link.

The information on the active tasks is presented as a table with the following columns:

Column	Description
Started	The date and time when the operation was started.
Operation	The name of the operation.
Status	Indicates the operation status. At present the only one possible is "In Progress", which means that the operation is under way.

The **Details** link beside a task leads to the **Task Details** page, where you can view the details of the operation.

When the operation is successfully completed or fails, the table is closed, and the **No active tasks at the moment** message appears.

Viewing Task Details

The **Task Details** page provides information on the Virtuozzo utilities messages when performing this or that operation. In other words, these messages would be displayed as if you performed a Container operation not by means of Parallels Power Panel, but by means of the command line (for example, over ssh).

The task details are presented as a table with the following columns:

Column Name	Description
Time	The time when a certain operation stage began.
Operation	The corresponding Virtuozzo utility message.
Status	The status of each of the steps the operation the operation consists of- In progress, Completed, or Failed.

The table is preceded by a heading informing you of the operation outcome, that is, whether it is **In progress**, **Completed**, or **Failed**

Viewing Error Details

The **Error Details** page provides specific information in case of an operation failure. When you are trying to perform an operation on a **Parallels Power Panel** page and the operation fails, the corresponding **Parallels Power Panel** page is refreshed with a thick red line across the page informing you of the failure and providing the **Details** link to learn more about this failure.

This page presents a complete response as to why the operation failed. This response might help you understand the reason for the failure.

If an operation fails, and a green line is displayed informing that the operation has been scheduled, it means that the failure occurred after the operation had been scheduled. That is why, it is desirable to always check the status of the scheduled operation by following the **Details** link at the right end of the green line to make sure that the operation has been successfully completed.

CHAPTER 6

Troubleshooting

Parallels Power Panel is an indispensable means for solving various kinds of problems related to the Container functioning. It is still more flexible due to its ability to work with not running Containers. The common groups of problems lending themselves readily to be handled by Parallels Power Panel boil down to the following:

- Services inaccessibility;
- Elusive problems.

You can also consult the **Network Problems** section to try to find out why the Container is inaccessible by network, and the **File Problems** section.

Note: The problem situations described in this chapter mainly concern Container with the Linux operating system installed. However, it can be also of use for those managing the Containers running Windows 2003 Server.


In This Chapter

Services Inaccessibility	62
Elusive Problems.....	62
Network Problems.....	63
File Problems	63

Services Inaccessibility

Various tasks you are accustomed to perform by means of your Container (accessing your web site or sending email and the like) may fail if the corresponding services are inaccessible.

Try consecutively the following three steps to determine the reason for this and do away with it:

- 1 Check if your Container is running. To this effect, log in either as a Service Container user or as your Container root/Administrator user and look at the status bar to determine if the Container is running or down. You can also check the status of your Container on the **Service Unavailable** screen by clicking the corresponding link provided on this screen. If the Container is down, click the **Start/Stop Container** link on the menu and press the **Start Container** button. Wait a little for the Container and all the services to start.
- 2  Go to the **Services** page (see page 38) and check the status of the service in question. The service must be running for the corresponding functionality to be accessible. For example, `psa` and `mysqld` must be running for the Plesk control panel to handle your requests, `httpd` - for your web site to function properly, `sshd` - for the Container to be accessible by `ssh`, `sendmail` - for you to be able to send email, `popa3d` - to receive email by the POP3 protocol, etc. You may also try to stop the `iptables` service to see if it solves the problem, because some `iptables` rules might prevent certain network connections.
 1. Go to the **Resources** page (see page 27) to determine if your Container is short of any resources. If some of the resources are marked in yellow or red, this is a hazardous situation that should be resolved immediately.

If the Plesk control panel is installed inside your Container and you are working with this panel, the **Service Unavailable** screen may sometimes be displayed when you are trying to perform this or that Plesk-related operation. This situation is normally handled as described above. However, in case none of the recommended measures works, you may have to reinstall the Plesk control panel into the Container, as the Plesk installation might be corrupted.

Elusive Problems

Sometimes it is hard to determine the exact reason for a problem. The problem might persist despite any actions undertaken. Such problems call for going back to an earlier state of the Container with these problems missing. This change-over is usually effected by means of:

- 1 Restoring the Container from a working backup (see page 23);
- 2 Reinstalling the Container (see page 20);

Note: It is for you to decide which way suits you most. Generally, these two options are applicable if you can start your Container to copy the valuable information from it. To assure a safe data saving in the situation where you cannot start the Container, repairing your Container is the most advisable problem-solving option.


- 3 Mounting your Container in the repair mode and copying the valuable personal data to a secure place outside the Container. Using the repair mode is covered in the **Repairing Container** section (on page 22).

Network Problems

Problem

Your Container is inaccessible by its hostname or IP address, or you cannot log in as root.

Solution

- If you are using the hostname, try to use the IP address, and vice versa.
- Ping your Container.
- Ask your provider to create a Service Container user for you. Log in to the Service Container which is responsible for managing all your Containers and check the problem Container hostname and IP address.
- Log in to the Service Container and change the Container root/Administrator password.
-  Log in to the Service Container and disable the `iptables` service inside the problem Container.

File Problems

Parallels Power Panel is tuned to not allow giant files to be uploaded to Containers. There is a maximal file size (e.g. 512 Mb, but it may be any other value) allowed to be uploaded to a Container by means of Parallels Power Panel. If you need to upload larger files to your Container, you should contact your service provider.

Index

A

Active Tasks Monitoring • 59

B

Backing Up and Restoring Container
 backup details • 24
 operations on backups • 23

C

Changing Container Password • 19
 Confirming Container Reinstallation • 21
 Confixx Control Panel
 logging in • 52
 Container Managing
 accessing via RDP • 55
 accessing via SSH • 53
 backing up • 23
 Confirming VE Reinstallation • 21
 logging in • 7
 rebooting • 15
 reinstalling • 20
 repairing • 22
 restarting • 15
 starting • 15
 stopping • 15
 Container Operations • 15

D

Directories Operations • See Folders
 Operations
 adding directories • See adding folders
 copying directories • See copying folders
 creating directories • See creating folder
 editing directories properties • See editing
 folder properties
 moving directories • See moving folders

E

Error Details • 60

F

Files Operations • 16

adding files • 18
 copying files • 18
 creating text file • 17
 editing file properties • 19
 editing text file • 18
 moving files • 18

Firewall

access rules • 44
 chains • 43
 editing rules in advanced mode • 50
 editing rules in normal mode • 44
 general notions • 43

Folders Operations • 16

adding folders • See adding files
 copying folders • 18
 creating folder • 17
 editing folder properties • 19
 moving folders • 18

H

History of Container Status Changes • 57

I

Installing Plesk • 50
 Introduction • 6

L

Logging In to Confixx Control Panel • 52
 Logging In to Container • 7
 Logging In to Plesk Control Panel • 51
 Logs

alerts log • 57
 history of Container status changes • 57
 overview • 56
 traffic log • 58

M

Mail • 62

N

Network Problems • 63

O

Operations Monitoring

- active tasks • 59
- error details • 60
- general overview • 56
- task details • 59

P

- Password
 - changing root • 19
- Plesk Control Panel
 - installing • 50
 - logging in • 51
- Power Panel Interface Customizing • 13
- Processes Managing • 41

R

- Reinstalling Container • 20
- Remote Desktop Connection • 55
- Repairing Container • 22
- Resources
 - monitoring • 27
 - monitoring resources • 27
- Resources Alerts Log • 57
- Restarting Container • 15

S

- Selecting Reinstallation Type • 21
- Services
 - service details • 39
- Services and Processes Managing • 37
- Services Inaccessibility • 62
- Signals • 41
- SSH
 - connecting to Container • 53
- Starting and Stopping Container • 15

T

- Task Details Monitoring • 59
- Traffic Log • 58
- Troubleshooting • 61

W

- Website • 62